

# Modeling chemical reactions with the Amsterdam Modeling Suite and the ReaxFF engine

## Table of Contents

|   |          |
|---|----------|
| <b>Downloads and setting-up AMS</b> .....                             | <b>1</b> |
| <b>Chemical vapor deposition of silica on a silicon surface</b> ..... | <b>1</b> |
| 1. Setting-up the Si substrate .....                                  | 1        |
| 2. Equilibration .....  | 2        |
| 3. Molecule Gun .....   | 3        |
| 4. Running the simulation .....                                       | 4        |
| <b>Combustion reaction of methane</b> .....                           | <b>4</b> |
| 1. Building the structure .....                                       | 5        |
| 2. Setting-up the combustion reaction.....                            | 5        |
| 3. Analysis .....   | 6        |
| 3.1. Energies .....   | 6        |
| 3.2. Molecules .....  | 6        |
| 3.3. Chemical reactions and mechanisms .....                          | 7        |


## Downloads and setting-up AMS

We will use the [Chemistry\\_with\\_ReaxFF](#) directory as the root for AMS jobs. All required files should already be in there.

If you are working on your local machine, you can download the files from the link:  
<https://www.scm.com/wp-content/uploads/Structures.zip>

## Chemical vapor deposition of silica on a silicon surface

The overall reaction for silica deposition is as follow:



The simulation described below was inspired from the tutorial [Simulating Chemical Vapor Deposition](#).

### 1. Setting-up the Si substrate

First, you will download and import the starting structure, visualize it, and create two regions. One region will be used to fix the bottom two layers of atoms in order to model that the

substrate is connected to a support. The second region will be used to control the temperature of the simulation.

- a) Start the AMS program. This will open AMSJobs.
- b) Open a new input window by clicking on [SCM → New Input](#).
- c) Import the Si100 structure from [File → Import System](#). Then browse to the location of the file you just downloaded and click [Open](#).

You can orient (translate) the structure by left-clicking (right-clicking) on the molecule area and by moving the mouse. You can zoom in and out with the scroll wheel of the mouse. Furthermore, you can orient the molecule in the yz, xz, and xy planes with the shortcuts ctrl+1, ctrl+2, and ctrl+3, respectively (cmd for MacOS).

- a) Select the ReaxFF engine from [ADF → ReaxFF](#). The periodicity should be set to [Slab](#), if not already set.
- b) Define 2 regions as follow:  
Open the Regions panel from [Model → Regions](#). Orient the molecule in the xz plane (cmd+2) for a better view. Then select the 2 bottom layers of Si: hold the shift key then left-click and drag the pointer over the atoms you want to select. Click the + button on the Region panel. Rename *Region\_1* to *fixed*.

Before you make a new selection, be sure to unselect all atoms by left-clicking an empty area next the molecule.

Proceed similarly to select the atoms of the 2 layers right above the fixed region. Rename this region to *thermo*. Atoms in the *fixed* and *thermo* regions should not overlap! Now we can apply the constraint to the fixed atoms.

- a) Click [Model → Geometry Constraints and PES Scan](#).
- b) Select an atom of the bottom *fixed* group.
- c) Click the + button left of *fixed* (*fixed position*).

## 2. Equilibration

We will now setup the system and perform a short equilibration of the substrate.

- a) From the [Main](#) tab, select [Task Molecular Dynamics](#).
- b) Click the [folder](#) button next the [Force field](#) and search for CHONSi.ff
- c) Click the > button next [Molecular Dynamics](#) and set the number of steps to 20000.

Note that this a rather short equilibration and a more reasonable equilibration would be of hundreds of ps (i.e. 400000 steps).

- d) Set the [Sample frequency](#) to 1000, the [Initial temperature](#) to 500 K, and the [Checkpoint Frequency](#) to 1000000.

Now we can add the thermostat to the *thermo* region to control the temperature of the simulation.

- a) Click the > symbol next [Thermostat](#).
- b) Click the + button. Select [NHC](#), set the [Temperature](#) to 500 K, and the [Damping constant](#) to 100 fs.
- c) Select the *thermo* region next to [Atoms in region](#).

Save and run the simulation. Click [File](#) → [Save](#), give it a name (e.g. Si100\_ReaxFF\_equil). Select the simulation on [AMSjobs](#) and click [Job](#) → [Run](#). When the simulation finishes, a pop-up window will ask you to update the coordinates, select use MD velocities and click Yes, new job. From the updated AMSinput, save the settings for the next simulation from [File](#) → [Save as...](#) and give it a name (e.g. Ge100\_ReaxFF\_CVD).

### 3. Molecule Gun

To model the CVD simulation, we will throw reactant molecules to the surface with an initial speed at regular time intervals during an MD/fbMC simulation. In order to project particles to the surface, we will use the Molecule Gun, as implemented in AMS. Let's start by setting the MD and by importing the reactants i.e. SiH<sub>4</sub> and O<sub>2</sub>.

- a) Go to [Model](#) → [MD](#) and increase the number of steps to 3000000.

To import the reactants, do the following.

- a) Download SiH<sub>4</sub>.xyz.
- b) Go to [Model](#) → [Regions](#), click [File](#) → [Import System](#) and select the SiH<sub>4</sub>.xyz file

If the imported molecule appears in the slab, you can move it above the surface by right clicking on it and moving the mouse up. The initial position of the reactants is not important.

- c) With the atoms of the SiH<sub>4</sub> molecule selected, click the + button and rename the region as SiH<sub>4</sub>.
- d) Repeat the steps above to import O<sub>2</sub>.xyz and create the O<sub>2</sub> region.

Now we can setup the molecule gun.

- a) Go to [Model](#) → [Molecule Gun](#), click the + button.
- b) Select SiH<sub>4</sub> next the [System](#), set [Mole fraction](#) to 1, [Frequency](#) to 5000, [Start Step](#) to 1.
- c) Set the [Fractional coords box](#) to 0, 1, 0, 1, 45, 50.
- d) Enable [Rotate](#).
- e) Click the + next to [Velocity dummies](#). Two dummy atoms should appear in the slab region, one blue and one white.
- f) Click the - button next to [Velocity direction](#) to remove the preset.
- g) Select the top dummy atom, hold shift, select the bottom dummy, release shift, and click the + button next the [Velocity direction](#). You should see Xx(297),Xx(296) appear.

These last few steps define the direction of the velocity for the molecule gun. It is important that the velocity direction, defined by the dummy atoms, go from the top dummy to the bottom dummy, in the z-direction. You can verify that the indices next the Xx symbols (here 297 and 296) indicate the top dummy (index 297) and second dummy (index 296).

h) set the **Energy** to 0.05 eV, the **Atom Temperature** to 450 K, and the **Contact distance** to 3 Å.

Proceed similarly to setup the molecule gun for the O<sub>2</sub> molecule. Click the + button to add a molecule, select the O<sub>2</sub> group, and provide the same settings as above **but the Mole fraction should be set to 2**. To set the velocity direction, skip the step (d) and (e), as we can reuse the dummy atoms created above. Just select the dummies in the right order and set the velocity direction (as in step f).

With these settings, the molecule gun will try to add a molecule every 5000 steps in the direction defined by the dummies, with an energy of 0.05 eV and an internal temperature of 450 K. The molecules will be inserted at 3.0 Å from the highest z-coordinates of the atoms underneath the random xy position.

Finally, some molecules can eventually bounce back to the vacuum, or some gases will escape the surface, hence it is a good idea to remove these molecules as they cross a given xy plane. This can be achieved by adding a molecule sink.

- a) Switch to **Model** → **Molecule Sink**.
- b) Click the + button, set the **Formula** to \* in order to include all types of molecules.
- c) Set **Safe box** to 0, 1, 0, 1, -100, 100, **Frequency** to 5000, and **Start step** to 1.

These last settings will define a molecule sink in the xy planes located at 100 Å and -100 Å in the z direction. The molecule sinks will delete all molecules that cross these limiting planes every 5000 steps starting at step 1.


Note that we also put a molecule sink at -100 Å because some molecules can cross the thin slab toward large negative z direction.

#### 4. Running the simulation

Save and run the simulation. Click **File** → **Save**. Select the simulation on **AMSjobs** and click **Job** → **Run**. This simulation might take a while so we will be moving on to the second example and we will get back to the results later.

### Combustion reaction of methane

In this second example, we will simulate the combustion of methane in oxygen. The general chemical reaction is as follow:



The simulation described below was inspired from the tutorials [Combustion simulation with ReaxFF](#) and [Detecting reactions from MD trajectories: ChemTraYzer2](#).

## 1. Building the structure

We will start by setting up the atomistic system by randomly inserting O<sub>2</sub> and CH<sub>4</sub> molecules in a simulation box. This can be easily achieved with the Packmol interface of the Builder.

- a) Open a new input window by clicking on [SCM → New Input](#).
- b) Switch to the ReaxFF engine from [ADF → ReaxFF](#).
- c) Click [Edit → Builder](#).

With the Builder you can define the size of the simulation box, the type of molecules to fill the box, and the number of each molecule in the box. The tool will display the corresponding density (at the bottom).

For full combustion we need at least 2 oxygen molecules for each methane molecule. We will use 50 molecules of CH<sub>4</sub> for 120 molecules of O<sub>2</sub> in order to boost the combustion.

- a) [Fill box with 50 copies of](#) methane i.e. type methane and select [CH<sub>4</sub>: Methane \(ADF\)](#).
- b) Click the + button next to [Molecules](#) to add a second field and [Fill box with 120 copies of](#) oxygen molecules i.e. type O<sub>2</sub> and select [O<sub>2</sub> \(ADF\)](#).

This should correspond to a density of 0.9632 g/mL, which is high but is required to observe the combustion reaction in the short timescale of the simulation.

Note that right above the density information, there are some advanced settings related to the Packmol algorithm.

To generate the atomic structure, click [Generate Molecules](#). You can then [Close](#) to exit the builder.

## 2. Setting-up the combustion reaction

We will now define the settings for the MD simulation. We will perform an NVT simulation (i.e. in the canonical ensemble) at high temperature, in order to speed-up the combustion reaction.

- a) From the [Main](#) tab, select the [CHO.ff Force field](#).
- b) Click the > button next to [Molecular Dynamics](#).
- c) Set the [Number of steps](#) to 30000.
- d) Increase the [Checkpoint frequency](#) to a large number e.g. 100000.

Now we can setup the thermostat to control the temperature of the simulation.

- a) Click the > button next to [Thermostat](#).

- b) Add a thermostat with the + button.
- c) Select the [NHC Thermostat](#) and set the [Temperature](#) to 3500 K.
- d) Set the [Damping constant](#) to 100 fs.

Save and run the simulation. Click [File](#) → [Save](#) and find a good name for your simulation. Select the simulation in the AMSjobs window and click [Job](#) → [Run](#).

### 3. Analysis

#### 3.1. Energies

No need for the simulation to be finished to start the analysis.

- a) From AMSjobs, click [SCM](#) → [Movie](#) to observe the simulations as it goes.

From AMSmovie, you can rotate, translate, orient the molecules as in AMSinput. Use the sliding bar to advance the simulation and to select a desired frame. You can also play and pause the movie with the corresponding buttons.

Let's have a look at some graphs. The total energy is shown by default. We can add in a separate graph the Kinetic and Potential energy.

- a) Click [Graph](#) → [Add graph](#).
- b) Click [MD Properties](#) → [Kinetic energy](#).
- c) Click [MD Properties](#) → [Potential energy](#).
- d) [Graph](#) → [Curve on Right Axes](#).

You can verify that the sum of the Kinetic plus the Potential energy is equal to the Total energy. Since the reaction is exothermic, the reaction releases energy and consequently, the total energy is decreasing.


#### 3.2. Molecules

We will now analyze the various molecules created during the reactive simulation.

- a) From [AMSmovie](#) click [MD Properties](#) → [Molecules](#).

The molecule window is composed of a few buttons at the top to sort the molecules either alphabetically ([Molecules](#)), by maximum number ([Max#](#)), or by averaged number ([Ave#](#)). Next there are two additional headers [Graph](#) and [Show](#). All checkboxes under the [Show](#) column are checked meaning that all molecules are currently shown in the movie panel. You can display only certain molecules, all, or none by checking the corresponding boxes. If you check a box in the [Graph](#) column, this will display the graph corresponding to the number of occurrences of that specific molecule as a function of MD step.

As a reminder, the combustion reaction is as follow:



As we can see from the long list of molecules based on the simulation, there are an ensemble of additional (intermediate) species that have been created.

a) Select from the [Show](#) column only the reactants and products of the reaction.

We can see that indeed, CH<sub>4</sub> and O<sub>2</sub> are consumed, while CO<sub>2</sub> and H<sub>2</sub>O are produced.

Note that it is possible that you did not produce some of the products. This could be because the simulation is not yet finished, and you should keep running the simulation.

### 3.3. Chemical reactions and mechanisms

In order to get further insights in the combustion reaction, we will use the ChemTraYzer2 tool. ChemTraYzer2 will analyze all molecules formed along the simulation, keep track of the events, and provide a summary of the reactions, including statistics and rate constants for the reactions.

a) From AMSmovie, select [MD Properties](#) → [Reaction detection ChemTraYzer2](#).

We will keep all defaults settings and hit [Run ChemTraYzer2](#) at the bottom. A new window opens with a list of the reactions identified by ChemTraYzer2. This window is split into two sections. The upper one lists all reactions by name, while the lower one lists each reaction's individual occurrences ordered by time. In the top section, reactions are reported in SMILES format as well as in molecular format.

a) Click the upper search field and type in CO<sub>2</sub>.

b) Select the first reaction in the upper panel.

c) Click the top line of the bottom panel.

Now only the corresponding molecules from the selected reaction are shown in the movie panel of AMSmovie. You can observe the full reaction step-by-step by clicking on the left and right arrow keys on the keyboard.

In the case the molecules of the reaction you observe are crossing the periodic boundaries, you can display the entire molecule from [View](#) → [Periodic](#) → [Periodic View Type](#) → [Complete Molecules](#).